Container 'matrix-element'

Ressourcen

- 0.25 GB RAM
- 1 Cores
- 3 GB HDD (root-fs)

System

- interne IPs
  - 10.2.0.15, fd00:10:2:0::15

Dienste

- element-web (via NGINX)

Installation

- Standard-Template mit Benutzern

NGINX

1. NGINX installieren
   - **sudo apt-get install nginx**
2. Konfigurationen erstellen

```
server {
    listen 80 default_server;
    listen [::]:80 default_server;

    root /var/www/public_html;

    index index.html;

    server_name _;

        location / {
        # First attempt to serve request as file, then
        # as directory, then fall back to displaying a 404.
        try_files $uri $uri/ =404;
    }
}
```

3. Webverzeichnis erstellen
   - **sudo mkdir -p /var/www/public_html**
4. Installation von Element-web (letztes tar.gz von https://github.com/vector-im/element-web/releases)
   - **wget https://github.com/vector-im/element-web/releases/download/v1.7.22/element-v1.7.22.tar.gz**
   - **tar --strip-components=1 --extract --gunzip --file=element-v1.7.22.tar.gz --directory=/var/www/public_html/**
   - **sudo cp /var/www/public_html/config.sample.json /var/www/public_html/config.json**
   - **sudo chown -R www-data:www-data /var/www/public_html**
5. Konfigurationen anpassen

```
{
    "default_server_config": {
        "m.homeserver": {
            "base_url": "https://erfurt.chat",
            "server_name": "erfurt.chat"
        },
        "m.identity_server": {
            "base_url": "https://vector.im"
        }
    },
    "disable_custom_urls": false,
    "disable_guests": false,
    "disable_login_language_selector": false,
    "disable_3pid_login": false,
    "brand": "erfurt.chat",
    "integrations_ui_url": "https://scalar.vector.im/",
    "integrations_rest_url": "https://scalar.vector.im/api",
    "integrations_widgets_urls": [
        "https://scalar.vector.im/_matrix/integrations/v1",
        "https://scalar.vector.im/api",
        "https://scalar-staging.vector.im/_matrix/integrations/v1",
        "https://scalar-staging.vector.im/api",
        "https://scalar-staging.riot.im/scalar/api"
    ],
    "bug_report_endpoint_url": "https://element.io/bugreports/submit",
    "defaultCountryCode": "DE",
    "showLabsSettings": false,
    "features": {
        "feature_new_spinner": false
    },
    "default_federate": true,
    "default_theme": "light",
    "roomDirectory": {
        "servers": [
            "erfurt.chat",
            "matrix.org"
        ]
    },
    "piwik": false,
    "enable_presence_by_hs_url": {
        "https://matrix.org": false,
        "https://matrix-client.matrix.org": false
    },
    "settingDefaults": {
        "breadcrumbs": true
    },
    "jitsi": {
        "preferredDomain": "jitsi.riot.im"
    }
}
```

6. Dienst aktivieren und neustarten
    - **sudo systemctl enable nginx.service**
    - **sudo systemctl restart nginx.service**

Dauerhafter Link zu diesem Dokument:
https://wiki.technikkultur-erfurt.de/dienste:bytecluster0002:matrix-element?rev=1614812211

Dokument zuletzt bearbeitet am: **03.03.2021 22:56**

Verein zur Förderung von Technikkultur in Erfurt e.V
https://wiki.technikkultur-erfurt.de/